

CA Unified Infrastructure Management[®] Unified Reporter

TM

Installation Guide

8.0



Document Revision History

Document Version	Date	Changes
1.0	September 2014	Initial version for UR 8.0.

Copyright Notice

This online help system (the "System") is for your informational purposes only and is subject to change or withdrawal by CA at any time.

This System may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of CA. This System is confidential and proprietary information of CA and protected by the copyright laws of the United States and international treaties. This System may not be disclosed by you or used for any purpose other than as may be permitted in a separate agreement between you and CA governing your use of the CA software to which the System relates (the "CA Software"). Such agreement is not modified in any way by the terms of this notice.

Notwithstanding the foregoing, if you are a licensed user of the CA Software you may make one copy of the System for internal use by you and your employees, provided that all CA copyright notices and legends are affixed to the reproduced copy.

The right to make a copy of the System is limited to the period during which the license for the CA Software remains in full force and effect. Should the license terminate for any reason, it shall be your responsibility to certify in writing to CA that all copies and partial copies of the System have been destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, CA PROVIDES THIS SYSTEM "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NONINFRINGEMENT. IN NO EVENT WILL CA BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS SYSTEM, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF CA IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The manufacturer of this System is CA.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2014 CA. All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

Legal information on third-party and public domain software used in this product is documented in the *Third-Party Licenses and Terms of Use* (http://docs.nimsoft.com/prodhelp/en_US/Library/Legal.html).

Contact CA

Contact CA Support

For your convenience, CA Technologies provides one site where you can access the information that you need for your Home Office, Small Business, and Enterprise CA Technologies products. At <http://ca.com/support>, you can access the following resources:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- CA Support policies and guidelines
- Other helpful resources appropriate for your product

Providing Feedback About Product Documentation

Send comments or questions about CA Technologies product documentation to nimsoft.techpubs@ca.com.

To provide feedback about general CA Technologies product documentation, complete our short customer survey which is available on the support website at <http://ca.com/docs>.

Contents

Chapter 1: Introduction	7
Before Installing UR.....	7
Back up Your Databases.....	7
Oracle Users Must Create a New Tablespace.....	7
JVM Requirement.....	8
Chapter 2: Installing Unified Reporter	9
Install Unified Reporter.....	9
Configure Mail Server Settings.....	11
Chapter 3: Uninstall Unified Reporter	13

Chapter 1: Introduction

Unified Reporter is an optional component for CA Unified Infrastructure Management that provides advanced reporting for the Unified Management Portal (UMP). You can run the out-of-box (OOB) reports that are provided. You can create your own ad hoc reports or customize the OOB reports with iReport.

This section contains the following topics:

[Before Installing UR](#) (see page 7)

Before Installing UR

Do the tasks described in this section before you install UR.

Back up Your Databases

Before you upgrade, it is recommended that you back up the UIM database and the UR repository database. Backing up these databases ensures that your monitoring data, and any Unified Reports you have created can be restored.

Note: The default UIM database name is *CA_UIM*. The default UR repository database name is *jasperserver* in UR 1.9, and *unifiedreporter* in versions of UR 6.5 and later.

Oracle Users Must Create a New Tablespace

Valid for first-time installations

When you install UR for the first time, the installer guides you through setting up a database connection. If Oracle is your database provider, the installer prompts you to enter a username and password for an Oracle tablespace. You *cannot* use the same username and password from the NM installation, or the UR installer will display a warning message, and not allow you to proceed.

To complete the UR installation, you must create a new username and password on the Oracle server, and enter this username and password in the Database Connection panel of the installer.

JVM Requirement

To run the installer, you must have the Java Virtual Machine (JVM) 1.6.x installed on the machine. You can verify the supported JVM versions by downloading the [UIM Compatibility Matrix](#).

To verify that you have a supported JVM, follow these steps:

1. At the command prompt, enter the following command:
`java -version`
If the listed version is 1.6.x, proceed to the next section. If the command fails, go to the next step.
2. If you believe your system has JVM version 1.6.x, but the previous step failed, make sure that the JVM is part of the system PATH environment variable.
3. If there is no directory on the system for Java, install it as follows:
 - a. Obtain a Java distribution from <http://www.java.com> (not affiliated with CA), and install it according to the directions at that site.
 - b. Perform step 2 to ensure that the JVM is included in the PATH environment variable.

Important! Ensure that you get the right package (32-bit or 64-bit) for your operating system. For example, 64-bit operating system requires a 64-bit JVM.

Chapter 2: Installing Unified Reporter

This section describes how to install UR.

This section contains the following topics:

[Install Unified Reporter](#) (see page 9)

[Configure Mail Server Settings](#) (see page 11)

Install Unified Reporter

You can deploy UR to any robot where UMP is installed and running. However, the installer must be executed from the system running the primary hub.

Follow these steps:

1. Log in to the [CA Customer Support Center](#) site.
2. Download the installation package for your OS.
3. Run the installer from the system running the primary hub:

- **Windows:**

Double-click on the installUR.exe file.

- **Linux:**

```
./installUR_linux.bin -i [gui | console]
```

- **Solaris:**

```
./installUR_solaris.bin -i [gui | console]
```

The GUI mode launches the installation wizard and the console mode runs the installer in command-line mode. When launching the installer from the command line, always include the **-i gui** or **console** argument.

The following instructions assume you are running the installation in gui mode, but both modes prompt you for the same information.

4. Click **Next** in the Introduction panel.

5. Browse to the location of the Unified Infrastructure Manager installation.

By default, UIM is installed in the following locations:

- **Windows 32-bit:**
C:\Program Files\Nimsoft
- **Windows 64-bit:**
C:\Program Files (x86)\Nimsoft
- **Linux:**
/opt/nimsoft
- **Solaris:**
/opt/nimsoft

6. Enter the username and password for the administrative UIM user.
7. Select the UIM robot from the **Robot** list where you want to install Unified Reporter.

Note:

- If you are upgrading, a dialog informs you of an existing instance of UR on the robot you selected. Click **Proceed**, and then go to step 10.
- If the **Invalid Upgrade/Reinstall** dialog appears, you are attempting an upgrade that is not supported. For the supported upgrade path, see the *UIM Compatibility Matrix* at: http://support.nimsoft.com/downloads/doc/NMSCompatibility_SupportMatrix_current.pdf.

8. Update the location of the data_engine if the location displayed is not correct.
9. In the Database Connection panel:

- Microsoft SQL: You can select **Database Authentication** or **Windows/NT Authentication**.
- Oracle: You must enter the username and password for a *new* tablespace--*not* the user configured for the data_engine--or the installer will not allow you to continue. After you complete the Database Connection panel, the system displays a summary of information about the installation. Proceed to step 10.
- MySQL: Click **Next**.

10. [Microsoft SQL and MySQL only:] Select the appropriate radio button in the Database Schema panel.
11. [Microsoft SQL and MySQL only:] Enter or select a database schema or catalog name.

Note: If you click the back arrow in your browser after creating a new schema/catalog, and then select **Create a new schema/catalog** again, the system will not allow you to use the same name a second time. In this case, you must select **Use an existing schema/catalog** to use the name you created previously.

12. In the summary panel about the installation, click **Install** if you are satisfied with the information displayed. Click **Previous** to edit information in earlier panels.

A panel with status bars displays while Unified Reporter installs.

When the installation is complete, a dialog notifies you that the installation was successful.

13. Click **Done**.

Unified Reporter is now installed and ready for use. See the *Unified Reporter Quick Start Guide*, available on docs.nimsoft.com, for an introduction to UR, and for information on configuring iReport.

Configure Mail Server Settings

If you schedule reports or run them in the background, you can specify email addresses to notify when the report completes. In order to use this feature, you must configure JasperReports Server to contact an email server.

Follow these steps::

1. Locate the `js.quartz.properties` file in the following directory on the system where UR is deployed:
`Nimsoft/probes/service/wasp/webapps/jasperserver-pro/WEB-INF/js.quartz.properties`.
2. Open the `js.quartz` file in a text editor.
3. Enter your values for the properties in the `js.quartz` file, referring to the two tables provided below.

Note: For mail server configuration, there is an additional property setting for authentication. This file is located on the system where UR is deployed in the following directory:

`Nimsoft/probes/service/wasp/webapps/jasperserver-pro/WEB-INF/applicationContext-report-scheduling.xml`.

4. After you have edited and saved these two files, restart the JasperReports Server.

Email Server Configuration Properties

`js.quartz.properties`

Property	Description
<code>report.scheduler.mail.sender.host</code>	The name of the computer hosting the mail server
<code>report.scheduler.mail.sender.username</code>	The name of the mail server user that JasperReports Server can use

report.scheduler.mail.sender.password	The password of the mail server user
report.scheduler.mail.sender.from	The address that appears in the From field on email notifications
report.scheduler.mail.sender.protocol	The protocol that the mail server uses. JasperReports Server only supports SMTP. Note: Your entry must be lower case--in this case, smtp .
report.scheduler.mail.sender.port	The port number that the mail server uses. For SMTP, the default is typically 25 (values other than 25 may not work in earlier JasperServer versions).

applicationContext-report-scheduling.xml

Property	Bean	Description
javaMailProperties key="mail.smtp.auth"	reportScheduler MailSender	If your mail server requires authentication, change this property from false to true.

Chapter 3: Uninstall Unified Reporter

Uninstall UR by executing the Uninstaller on the system running the primary hub. On Windows systems, the uninstaller can be launched from the Start menu shortcuts, or you can execute the `/UnifiedReporter/Uninstall_UnifiedReporter` file.

The Uninstaller updates the wasp probe configuration so that UR is no longer available for configuration or startup. The uninstaller does not remove the database tables supporting UR. Therefore, if it is a requirement that the UR files be removed, they must be removed manually.

To manually remove UR files:

1. Open Infrastructure Manager.
2. In the tree view, click on the robot for the hub where UMP and UR are installed.
3. Right-click the wasp probe in the top-right pane and choose **Deactivate** from the pop-up menu.
4. Remove UR from the wasp probe by following these steps:
 - a. Click the wasp probe to select it.
 - b. Press <Ctrl> and right-click the wasp probe, then choose **Raw Configure** from the pop-up menu.
 - c. Expand the webapps node.
 - d. Click the jasperserver-pro folder to select it.
 - e. Click **Delete Section**.
5. Remove the following files if present from the robot where UR was deployed:
 - `nimsoft/probes/service/wasp/tmp`
 - `nimsoft/probes/service/wasp/bin`
 - `nimsoft/probes/service/wasp/tmp_jasper.zip`
 - `nimsoft/probes/service/wasp/webapps/jasperserver-pro`
 - `nimsoft/probes/service/wasp/webapps/jasperserver-pro.war`
6. Activate the wasp probe.